



## LOOPER:MODE Launchpad Mini MK3 Installation

### To install LOOPER:MODE on your Launchpad Mini MK3:

- Copy the Script folders “LOOPER\_MODE\_Launchpad\_Mini\_MK3” and “Launchpad\_Mini\_MK3\_for\_LOOPER\_MODE” to your clipboard by right-clicking on it and choosing Copy.
- You will have to paste them into Ableton Live's MIDI Remote Scripts folder, as described below.

#### **In Live 10.1.3 and above:**

Create a folder named “Remote Scripts” in your User Library. Copy the folders into this folder.

#### **Up to version 10.1.2:**

##### *Mac OS X*

Open your Applications folder and right-click the Live application symbol. In the context menu, click on Show Package Contents.

In the Ableton Live package, navigate to Contents > App-Resources > MIDI Remote Scripts. Paste the folder you have copied to your clipboard into the "MIDI Remote Scripts" folder.

##### *Windows*

Go to Ableton Live's installation directory. By default, it is located here:

C: > Program Data > Ableton > Live 10 > Resources > MIDI Remote Scripts

Note: The Program Data folder may be hidden.

Paste the folder you have copied to your clipboard into the "MIDI Remote Scripts" folder.

- Re-launch Live
- In Live's Preferences, go to the Link/MIDI Tab and in the Control Surface area :
  - On one line, select :
    - Control Surface: **Launchpad Mini MK3 for LOOPER MODE**
    - Input: Launchpad Mini MK3 (LPMiniMK3 **DAW** Out)
    - Output: Launchpad Mini MK3 (LPMiniMK3 **DAW** In)
  - On a second line, select :
    - Control Surface: **LOOPER MODE Launchpad Mini MK3**
    - Input: Launchpad Mini MK3 (LPMiniMK3 **MIDI** Out)
    - Output: Launchpad Mini MK3 (LPMiniMK3 **MIDI** In)

To activate LOOPER:MODE on the Launchpad Mini MK3, press **the User button**.

The button will then turn Yellow. To switch back to the original User mode, press the button once again (it will be back to its normal color).